Games Translators

Version 6

© Copyright 2004 Alias Systems, a division of Silicon Graphics Limited ("Alias"). All images © Copyright Alias unless otherwise noted. All rights reserved.

Alias is a registered trademark and the swirl logo, the Maya logo, Conductors, Trax, IPR, Maya Shockwave 3D Exporter and MEL are trademarks of Alias in the United States and/or other countries worldwide. Maya is a registered trademark of Silicon Graphics, Inc. in the United States and/or other countries worldwide, used exclusively by Alias. SGI, IRIX, Open GL and Silicon Graphics are registered trademarks of Silicon Graphics, Inc. in the United States and/or other countries worldwide. mental ray and mental images are registered trademarks of mental images GmbH & CO. KG. in the United States and/or other countries. Lingo, Macromedia, Director, Shockwave and Macromedia Flash are trademarks or registered trademarks of Macromedia, Inc. Wacom is a trademark of Wacom Co., Ltd. NVidia is a registered trademark and Gforce is a trademark of NVidia Corporation. Linux is a registered trademark of Linus Torvalds. Intel and Pentium are registered trademarks of Intel Corporation. Red Hat is a registered trademark of Red Hat, Inc. ActiveX, Microsoft and Windows are either registered trademarks or trademarks of Microsoft Corporation in the United States and/or other countries. Mac, Macintosh and QuickTime are trademarks of Apple Computer, Inc., registered in the United States and other countries. Adobe, Adobe Illustrator, Photoshop and Acrobat are either registered trademarks or trademarks of Adobe Systems Incorporated. UNIX is a registered trademark, licensed exclusively through X/Open Company, Ltd. AutoCAD, Discreet Logic, Inferno and Flame are either registered trademarks or trademarks of Autodesk, Inc. in the USA and/or other countries. OpenFlight is a registered trademark of MultiGen Inc. Java is a registered trademark of Sun Microsystems, Inc. RenderMan is a registered trademark of Pixar Corporation. Softimage is either a registered trademark or trademark of Avid Technology, Inc. in the United States and/or other countries. All other trademarks, trade names, service marks, or product names mentioned herein are property of their respective owners.

This document contains proprietary and confidential information of Alias, and is protected by Federal copyright law and international intellectual property conventions and treaties. The contents of this document may not be disclosed to third parties, translated, copied, or duplicated in any form, in whole or in part, or by any means, electronic, mechanical, photocopying, recording or otherwise, without the express prior written consent of Alias. The information contained in this document is subject to change without notice. Neither Alias, nor its affiliates, nor their respective directors, officers, employees, or agents are responsible for any damages of any kind arising out of or resulting from the use of this material, including, without limitation, any lost profits or any other direct, indirect, special, incidental, or consequential damages or for technical or editorial omissions made herein.

ALIAS ■ 210 KING STREET EAST ■ TORONTO, CANADA M5A 1J7

Table of Contents

1 Introduction 7

Developer **Games data translators 7**

Introduction 7

Translator processing has two basic stages internally 7

Common options for the internal data base 8

Run a games translator 8

Customize and rebuild translators 8

Build the necessary translators 9

Installing on different platforms 10

Load translators in Maya 11

2 VRML2 Translator. 13

Developer **Games data translators 13**

VRML2 13

Overview of VRML2 13

VRML2 Features 13

Files required to use this plug-in. 14

Limitations. 14

Install the VRML2 translator 15

Set VRML2 properties in Maya 15

VRML2 Plug-ins. 15

Link Objects to Web Addresses with VRML2Link 16

Create preset VRML viewpoints 17

vrml2TagsWin attribute descriptions 17

Import a VRML2 file using wrl2ma 18

Menus 20

File 20

File > Export All > VRML2. 20

Animation Options 20

Export Options 21

Texture Options 22

VRML2 options 23

3 RTG Utility and File Format 27

Developer

Games data translators 27

RTG utility and file format 27

Overview of RTG translator 27

RTG Features. 27

Files required to use this plug-in. 27

Install the RTG translator 27

Menus 28

File 28

File > Export All > RTG. 28

RTG translator options 28

RTG Options 28

Animation Options 30

Export Options 30

Texture Options 32

4 Game Exchange 2 Translator 33

Developer

Games data translators 33

Games exchange 2 translator 33

Overview of GE2 translator 33

GE2 Features. 33

Files required to use this plug-in. 34

Install the GE2 translator 34

Menus 34

File 34

File > Export All > GE2 34

Domain Options 34

Animation Options 34

Export Options 36

Texture Options 37

Other Options 38

Debug Output 38

5 MDt API 41

Developer

Games data translators 41

Games export toolkit (MDt API) 41

Overview of Games export toolkit 41

Incorporate functions/ideas 41

Use the MDt library 42

Find API function documentation 42

Use the MDt API 43

Structure of the internal database 43

Animation 45

Minimal Program example 46

Basic Program example 46

Table of Contents

1 Introduction

Developer Games data translators

Introduction

This documentation provides information on how to use the Maya game translators.

Important note
Since Maya 4.0, we encourage you to use Maya's API directly. Several new functions have been added to API since the MDT layer was created for Maya 1.0 which means the need to use the MDT layer has reduced. For Macintosh OS X, the source code has also been moved to: /Applications/Alias/Maya 6.0/devkit/obsolete/games.

Maya game translators are provided for licensed Alias customers. The source code for the translators as well as the MDtApi is provided so that the supplied translators can be modified for site-specific customizations.

The game translators, VRML2, RTG and GE2, are written with an API interface layer (MDtApi). The MDtApi functions are implemented using the Maya API. MDtApi *does not* replace the Maya API in any form. The Dt functions are meant to ease the re-use of source code between the translators and different platforms and to provide example API source code.

The game translators are File Translator plug-ins accessed from the File > Export All or File > Export Selection menu items.

Translator processing has two basic stages internally

- Creating an internal database of information that allows for relatively easy access to the Maya scene information. This database can be considered as a grouping mechanism.
- Running the translator using the information from the data base.

This process divides into separate options that you need to define. The first set of options deals with the setup of the internal database, and the second with the actual options for the translator that you are going to run.

Common options for the internal data base

Animation options

including frame ranges, the level of requested animation

Export Options

including hierarchy information, tessellation parameters, verbose activity reporting

Texture Options

including shader evaluation parameters

Translator-specific options are described for each translator.

Run a games translator

The Maya games translators include VRML2 RTG and GE2.

Running a translator involves two processes:

- Loading the translator from the Window > Settings/Preferences > Plug-in Manager window.
- Starting the translation from either the File > Export All or File > Export Selection menu items or from within a MEL script, using the commands:

```
file -rename output_filename
file -exportAll
```

or

```
file -exportSelected
```

Customize and rebuild translators

The following shows you how to recompile and/or rebuild translators.

To recompile the translators:

1. Before you begin, you need to have a C++ compiler, such as:

   (IRIX and Linux) SGI C++ 7.3.1

   (Windows) Microsoft VC++ 6.0

   (Mac OS X) Metrowerks' CodeWarrior 7.1
2. You can recompile the translator by creating a local work area and populate it with the following directory tree:

   MDt/MDtApi

   MDt/include

MDt/lib

MDt/vrml2Export

MDt/rtgExport

MDt/ge2Export

3 Copy the respective directories from $MAYA_LOCATION/devkit/obsolete/games.

Maya contains Makefiles for CodeWarrior, SGI, and MS IDE project files that can be used to rebuild the translators.

Note	You may have to edit the Makefiles and customize the project files for specific Maya installation areas.

4 Build the MDtApi library first. This creates a static library used for the other translators. It is possible to create this as a LIB (Mac OS X), DSO (IRIX and Linux), or DLL (Windows) file, but for the moment it is easier to create a static library for updates and changes to the translators.

(IRIX and Linux) The libMDtApi.a will be copied to the lib directory and referenced from there.

(Windows) The libMDtApi.lib is found in the Release subdirectory and is referenced from there.

(Mac OS X) The libMDtApi.lib is found in the CFMSupport folder and is referenced from there.

Build the necessary translators

Note	For Mac OS X, you do not need to build any translators, since the libraries are already provided.

1 Copy the translator plug-in file to the user's Maya work area into the plug-ins directory. There should be a work area with a directory structure such as:

$HOME/maya/prefs

$HOME/maya/projects

$HOME/maya/plug-ins

$HOME/maya/scripts

Note	If the plug-ins or scripts directories are not present they should be created by the user.

2. Unload the current version of the plug-in from Windows > Settings/ Preferences > Plug-in Manager.
3. Compile the new version of the plug-in.
4. Place the new translator plug into the plug-ins directory, and the MEL option script into the scripts directory.
5. Reload the plug-in from Windows > Settings/Preferences > Plug-in Manager.
6. If the MEL option script has been modified, source it again so that the changes are updated within Maya. Else the changes will not be seen.
7. Run the translator.

Note	Replacing a plug-in without first unloading it will cause Maya to crash on IRIX or Linux, and will fail to copy the new version of the plug-in on Windows and Mac OS X.

Installing on different platforms

The direct translators for games are installed as a standard part of the Maya software under devkit/games.

The game translator directory structure is described in the following depending on which platform Maya is running.

Note	In the following directory locations it is assumed that for Windows, Maya is installed on drive C:. If this is not the case, change the “c:” references to the drive where it is installed.

The translator binary image .lib (Mac OS X), .so (IRIX and Linux) or .mll (Windows) files are in:

(IRIX and Linux) /usr/aw/maya/bin/plug-ins/

(Windows) C:\Program Files\Alias\Maya6.0\bin\plug-ins

(Mac OS X) /Applications/Maya 6.0/Application Support/plug-ins

The MEL script files used for user options are in:

(IRIX and Linux) /usr/aw/maya/scripts/others/

(Windows) C:\Program Files\Alias\Maya6.0\scripts

(Mac OS X) /Applications/Maya 6.0/Application Support/scripts

To run the translators, the binary plug-in and the MEL option files should be all that is needed. If the source code is necessary, it can be found under the devkit directory tree:

(IRIX and Linux) /usr/aw/maya/devkit/obsolete/games/

(Windows) C:\Program Files\Alias\Maya6.0\devkit\obsolete\games

(Mac OS X) /Applications/Maya 6.0/devkit/obsolete/games

These include the following directories:

- MDtApi
- include
- vrml2Export
- rtgExport
- ge2Export

Note You must create the lib directory yourself. The lib is not included by default.

Load translators in Maya

After you add the games plug-ins to the list of plug-ins, you still need to load the plug-ins to use them.

1. Select Windows > Settings/Preferences > Plug-in Manager to open the Plug-in Manager window and display the list of all known plug-ins.
2. Find the plug-in you need and click the loaded check box to load the plug-in. If you only turn on the auto load, you must restart Maya to load the plug-in.

2 VRML2 Translator

Developer Games data translators

VRML2

Overview of VRML2

The VRML2 translator lets you export Maya scene files into VRML2 format. NURBS surfaces are tessellated to polygons and then output.

Note	The VRML2 translator does not output all of the Maya feature set.

VRML2 Features

Outputs

- polygon geometry
- NURBS surfaces - tessellated into either triangles or quads
- hierarchy structure if wanted
- VRML2 primitives (if tagged)
- shader parameters
- textures - SGI RGBA image format
- rigid TRS animation
- vertex animation
- Camera information
- Light information

Commands

There is a MEL command included in the VRML2 translator. This command, *vrml2Tags*, let you define dynamic attributes onto objects that the translator queries and uses to define the output file.

Attributes

The following dynamic attributes can be defined and used with this translator.

- userAnimated boolean: On = force vertex animation processing
- VRML2Primitive: long, cube/plane

- VRML2Billboard: long, camera facing/Y facing/Z facing

Files required to use this plug-in

The files required for use of this plug-in are:

- vrml2Export.lib (Mac OS X), vrml2Export.so (IRIX and Linux), or vrml2Export.mll (Windows)
- vrml2TranslatorOpts.mel

Source code can be found in:

```
(IRIX and Linux) /devkit/obsolete/games/vrml2Export

(Windows)Program Files\Alias\Maya6.0\devkit\obsolete
\games\vrml2Export

(Mac OS X)Applications/maya 6.0/devkit/obsolete/games/
vrml2Export
```

Limitations

- On Mac OS X, the VRML2 Exporter does not export textures.
- The range for the light intensity in VRML2 is [0 to 1.0]. Maya doesn't have a limit. The translator assumes a scaling of [0-100] and divides down the Maya setting.
- No checks are made for negative scales. VRML2 defines scale to be greater than 0.
- Only SGI RGB/RGBA file textures are output. Microsoft's VRML2 viewer does not support this format. Cosmoplayer does read the texture files on both IRIX and Linux and Windows systems. You may have to set up the file associations on the Windows platform to run Netscape instead of Explore if the auto launch feature is used on Windows systems.
- You need to turn on Sample for Texture Options to get proper rotation of textures.
- There may be memory leaks in the translator. This is because not all of the intermediate internal structures are deleted (for instance, animating NURBS surfaces will create a noticeable memory leak with Maya 1.0 due to the tesselation).
- Vertex animation is based on the connection of the *inMesh* attribute, so this will cause more geometry to be considered animated that may be. For final results, you may want to clean up the history of non-animated tweaks.

A check for dynamic attribute called *userAnimated* to force usage has been added. Use the Add Attribute command to add *userAnimated* as a boolean flag and then set it ON for those objects that you want to force the vertex animation to recognize and use. This will mostly be for those objects that don't have history and an *inMesh* connection.

- Instanced geometry is output multiple times but doesn't get reused.

Install the VRML2 translator

You install the VRML2 translator plug-in using the Plug-in Manager.

1. Select **Windows > Settings/Preferences > Plug-in Manager** to display the list of all known plug-ins.
2. Click the loaded check box beside vrml2Export.so (IRIX and Linux), or vrml2Export.mll (Windows), or vrml2Export.lib (Mac OS X) to load the plug-in.

   If you only turn on the auto load, you must restart Maya to load the plug-in.

Set VRML2 properties in Maya

VRML2 Plug-ins

The vrml2Tags command lets you attach tags to objects that have no effect in Maya as dynamic Attributes, but will be added to the VRML2 file.

The vrml2Tags command is a MEL script file *vrml2Tags.mel* which is found in the scripts/other directory.

To set VRML2 properties:

1. Select the objects you want to create with VRML2 attributes.
2. Type *vrml2Tags* in the Command Line to run the vrml2Tags command. The following window displays.



3 Change the settings of the vrml2 tags in this window and click the Add button.



4 These attributes are now available for further changes in the Extra Attributes section of the object's Attribute Editor.

See the following for attribute descriptions and workflows.

Link Objects to Web Addresses with VRML2Link

The Link and Message attributes lets you create, verify, or remove hypertext links.

To link objects to web addresses

1 Select the object or objects you want to link.

2 Execute the vrml2Tags MEL command to display the current VRML2 tags information. Type *vrml2Tags* in the Command Line.

3 Press the Add button at the bottom of the window.

The attributes are now accessible from the selected object's Attribute Editor's Extra Attribute section.

4 In the vrml2 Link box, enter a Universal Resource Locator (URL). For example:

```
http://www.aw.sgi.com
```

You can also add a description of the destination using the form:

```
URL*DESCRIPTION
```

Where URL is the destination, the * (asterisk) is a separator, and DESCRIPTION is a description that will be displayed in the VRML browser when you point at the link.

For example:

```
http://www.alias.com*Alias Web Page
```

5 When you output the scene using File > Export All, the objects become active VRML links.

Create preset VRML viewpoints

Viewpoints are predefined camera positions and views in a VRML world. Viewpoints help viewers navigate your VRML worlds (for example, allowing them to return to an entrance point, or view close-ups of objects).

To create VRML viewpoints

1. Create a new camera.
2. Name the camera. Use a name that contains only valid VRML2 characters. This means do not use dashes or [] {}. For example, a valid VRML2 camera name would be `EntranceView`.
3. On the URL in the vrml2 Link field, type the name of the viewpoint this object will trigger, preceded by #. For example:

```
#EntranceView
```

vrml2TagsWin attribute descriptions

The following describes the attributes in the vrml2TagsWin. Whatever you set in the vrmlTags window displays and becomes editable in the Extra Attributes section of the object's Attribute Editor.

vrml2 Billboard menu

The VRML2 billBoard options include the standard VRML2 options, None,
X-Rotating, Y-Rotating, and Screen Aligned.

vrml2 primitive menu

The VRML2 primitive options include the standard VRML2 options, None, Box, Cone, Cylinder, Sphere, and Elevation Grid.

vrml2 Sensor menu

The VRML2 sensor options include the standard VRML2 options, None, Cylinder, Sphere, Plane, Proximity, Touch, and Visibility.

vrml2 Collision menu

The VRML2 collision options include the standard VRML2 options, None and Object.

Do All selected checkBox

This checkbox performs the Add/Update operation on the entire current selection list. If it is not turned on, the current item in the selection list as shown at the top of the vrml2TagsWin window is used.

This is only useful if multiple objects are currently selected.

Add and Update checkBox

This checkbox combines the add and update functions at the same time. When turned off, the Add operation creates the dynamic attributes on the objects and uses the default settings. When turned on, the currently displayed settings are used to assign to the attributes.

Add button

Click this button to create default dynamic attributes on the objects in the current selection list. See “Do All selected checkBox” and “Add and Update checkBox” options for details.

Delete button

Click this button to delete the VRML2 dynamic attributes on the objects in the current selection list. See “Do All selected checkBox” and “Add and Update checkBox” options for details.

Selection stepping controls

The four stepping control buttons let you select which item to use for the individual object of interest. This is only useful if multiple objects are currently selected.

The buttons from left to right are first object, previous object, next object, and last object.

The current object of interest is listed in the first line of the vrml2Tags window.

Close button

Click this button to close the VRML2 tags window.

Import a VRML2 file using wrl2ma

The wrl2ma stand-alone program lets you convert VRML2 files to Maya ASCII.

The vrml2 importers include:

(IRIX and Linux and Mac OS X) wrl2ma

(Windows) wrl2ma.exe

The conversion includes:

- geometry
- normals
- texture coordinates
- color per vertex

- shader parameters (Lambert and Phong)
- texture file references (in-line textures are not supported)

Note	Animation is not supported with this version.

To use wrl2ma

Specify the input .wrl file and the output .ma file, and also specify the extensions you want.

For example, type something similar to the following in a system shell or terminal:

```
wrl2ma -i Porsc911.wrl -o Porsc911.ma
```

This example converts the VRML file Porsc911.wrl to a Maya 6.0 ASCII file named Porsc911.ma. The command provides the following options:

Options	What it does
-h	Prints the help file
-i <inputFile>	Specifies the input file to convert
-o <outputFile>	Specifies the output file to save to
-m	Assume input file was output by Maya
-v	Prints verbose messages
-d	Uses a debugging aid to see how the libvrml97 scene parser parses the original VRML file.

Menus

File

File > Export All > VRML2

Animation Options

Range Control options

Loop

Enables the VRML2 option to loop the animation on playback.

Time Slider

Uses the start/end range from the time slider instead of from the settings in this window.

Enabled

Click to quickly disable any animation without resetting the ranges.

Start/End

The Start value specifies the frame to start the output from (integer values). The End value specifies the frame to end the output.

Step

This value defines the number of animated frames by which the animation is sampled between exported frames.

Frames per sec

This value specifies the VRML2 playback frame rate.

Animate

Click to turn on the following options. A check mark displays if the option is on and the option you select will animate.

Vertices

Animates vertex animation at each frame (can be slow for NURBS geometry).This option is off by default.

Transf

Animates transformation animation at each frame. This option is on by default.

Materials

Animates shader material parameter animation. This option is on by default.

Lights

Animates light parameter animation. This option is on by default.

Cameras

Controls camera process information.

Keyframe using Anim Curves

Output by Keyframes on Animation curves. This option is off by default. (**Note**: This is a future option and is not currently implemented.)

Export Options

These options determine what elements you want to export.

Hierarchy

World

A World hierarchy tells the VRML 2 translator not to export hierarchy. This means that all vertices use world space.

Flat

A Flat hierarchy means one level of hierarchy. Selecting Flat means that transformations use world space and vertices use local space. There is no hierarchy/parenting information. This is the default Hierarchy selection.

Full

A Full hierarchy exports the full DAG tree hierarchy. This means that transformations and vertices use local space. Full hierarchy/parenting information is available.

Joints

Allows NULL chains to be output for hierarchy information, mostly for skeletons/joints.

Export

All

Exports all scene information (everything visible in the scene). This is the default Export selection.

Picked

Exports everything picked in the scene (items lower in the DAG tree from the DAG nodes of picked objects are not included).

Active

Exports everything picked in the scene as well as any objects that are below them in the DAG tree.

Tesselation

Tri

Tessellates NURBS surfaces into triangles. This is the default Tessellation selection.

Quad

Tessellates NURBS surfaces into quads.

Include

Cameras

Allows Camera information to be collected for the database. This option is on by default.

Lights

Allows Light information to be collected for the database. This option is on by default.

Debug Info

Geo/Mat

Outputs a lot of information during the export process. Shape/material information is output here.

Cameras

Controls camera process information.

Lights

Controls light process information.

Texture Options

Evaluate

Uses convertSolidTx to create image files for both file and procedural textures. If turned off, Maya reads in the file textures as they are, and only converts the procedural textures.

Sample

Uses the 2D texture placement transformation information to generate the file image for output. For instance, the checker texture image consists of a checker board of 8x8 checkers. If Sample is off, the UV repeats are set to 1 internally, UV Rotate is set to 0.0 internally, and then the texture is processed. The result is that the checker image will be 2x2 (assuming the default 4 repeat).

Original

For file texture images, turn on to use a reference to the original file texture as defined in the texture node.

Resolution settings

Set the following X and Y texture resolution swatch sizes by entering a value and pressing Enter (IRIX and Linux and Windows) or Return (Mac OS X), or by dragging the slider.

X Tex Res/ Y Tex Res

Specifies the X or Y swatch size used for procedural textures.

Max X Tex Res/ Max Y Tex Res

Specifies the Max X or Y swatch size used for all textures. File textures larger than the size specified here are rescaled to the maximum size when the texture is computed with the convertSolidTx command.

Texture Search path

This is a list of directories to search for file textures if not found in the default list of directories obtained with workspace -q -rd .

VRML2 options

Navigation

This is the VRML2 navigation list. These settings control the initial set-up of the VRML browser (or viewer) when it opens the *.wrl* file. Click to turn on the following items (a check mark displays) to suit your needs.

Walk

Walk navigation is used to explore a virtual world on foot or in a vehicle that rests or hovers above the ground. It is strongly recommended that Walk navigation defines the up vector in the Y direction and provides some form of terrain and gravity to produce a walking or driving experience. If on, the browser supports collision detection. This option is off by default.

Examine

Examine navigation is used to view individual objects and often includes (but does not require) the ability to spin around an object and move the viewer closer or further away. This option is on by default.

Fly

Fly navigation is similar to Walk navigation except that terrain and gravity can be disabled or ignored. This option is off by default.

Any

If the Any navigation mode is selected, the browser chooses the navigation mode that best suits the content and provides a user interface that lets you change the navigation mode dynamically. If off, you cannot change the navigation mode and the browser only uses the modes specified in the list. This option is on by default.

None

None navigation disables and removes all browser-specific navigation user interface. This means that you can only navigate using mechanisms provided in the scene, such as Anchor nodes or scripts that include loadURL().This option is off by default.

Options: Headlight

This is the VRML2 headlight control option. When turned on, the viewer casts light on the scene. This option is on by default.

Navigation speed

The value in this box is the VRML2 navigation speed setting. Enter a new value and press Enter (IRIX, Linux and Windows)/Return (Mac OS X) or drag the slider if you want to change the initial speed of the viewer.

Float precision

This is the number of digits used after the decimal point.

Export

Click to turn on the following options. A check mark displays if the option is on and the Export option you select will export to VRML2.

Normals

Exports normals. This option is off by default.

Opposite

Flips the direction of generated normals (not normally needed).This option is off by default.

Textures

Exports textures.This option is on by default.

Long Lines

Allows long lines in output file.

Turn off to break the VRML text file into short lines (each value on a separate line). For instance, turn this off if you want to edit the output file with a text editor that does not handle lines longer than approximately 80 characters well (such as vi). This option is off by default.

Verbose

Acquires feedback during the translation. This option is off by default.

Launch viewer

If turned on, on completion of the translator Maya launches Netscape (IRIX and Linux) or an associated program for files with the .wrl extension (Windows).This option is off by default, and not available on Mac OSX.

Compressed

Runs the *gzip* program to compress the output file. The file extension will still be .wrl. On Windows, the *gzip.exe* program should be located in the execution path. This option is off by default.

Reversed

Reverses the winding for NURBS surfaces that are single- sided and have the Opposite turned on. This option is on by default.

ColorPerVertex

Enables the output of color per vertex if it is available for objects being output. This option is off by default.

Texture path

The textures are saved in the directory you specify in this box.

Run script when done

Click the Browse button to select a script or enter the name of the script to run after the translation is complete. A system() call is made so the executable command should be found on the PATH statement.

Append file name to script

This option determines whether or not the output file name is appended to the end of the command line submitted. This option is on by default.

VRML2 Translator | 2

Developer > File > Export All > VRML2

3 RTG Utility and File Format

Developer **Games data translators**

RTG utility and file format

Overview of RTG translator

The RTG translator provides a method to output the Maya scene information generically. The source code is included so that site-specific changes or customizations can be done.

RTG Features

Outputs

- polygon geometry
- NURBS surfaces - tessellated into either triangles or quads
- hierarchy structure if wanted
- shader parameters
- textures - SGI RGBA image format
- rigid TRS animation

Commands

There are no MEL commands included with the RTG translator.

Attributes

There are no specific Maya attributes queried in the RTG translator.

Files required to use this plug-in

The files required for use of this plug-in are:

- rtgExport.lib (Mac OS X), rtgExport.so (IRIX and Linux), or rtgExport.mll (Windows)
- rtgTranslatorOpts.mel

Source code can be found in: devkit/obsolete/games/rtgExport

Install the RTG translator

You install the RTG translator plug-in using the Plug-in Manager.

1. Select **Windows > Settings/Preferences > Plug-in Manager** to display the list of all known plug-ins.

2 To load the plug-in, click the loaded check box beside rtgExport.so, rtgExport.mll, or rtgExport.lib (depending on your operating system).

If you only turn on the auto load, you must restart Maya to load the plug-in.

Menus

File

File > Export All > RTG

RTG translator options

RTG Options

Base options

Click to turn on the following options. A check mark displays if the option is on and the option you select will be enabled during output.

Verbose

Acquires feedback during the translation. This option is off by default.

Reversed

Reverses the winding for NURBS surfaces that are single- sided and have the Opposite turned on. This option should be turned on by default.

Image Format

Choose either SGI RGB or Alias PIX from the list provided.

Format

IRIX and Linux/DOS

Select one of these options to determine whether the output ASCII files are written in IRIX and Linux <lf> or DOS <cr><lf> format. Click to turn on the following options. A check mark displays if the option is on and the format option you select will output to rtg.

V1.8 Compatible

Enables some of the PA RTG 1.8 output formats.

V Normals

Outputs Vertex Normals.

P Normals

Outputs Polygon Normals.

V Colors

Outputs Vertex Colors.

UV Coords

Games Translators Outputs UV coordinates.

indexCnt

Outputs index counters at the beginning of each list entry.

Degrees

Outputs the transformation angle in degrees instead of radians.

Materials

Outputs shading group Material properties.

MultiTexture

Outputs separate texture images for those material properties that are texture mapped, including: diffuse, bump, translucence, specular color, cosinePower etc.

MDecomp

Decomposes the transformation matrix into components of T/R/S.

Pivots

Outputs pivot information.

Transforms

Outputs transformation information.

Local Xform

Outputs the local transformation matrix [4x4].

Animation

Outputs T/R/S animation.

All Nodes

Forces all nodes to output animation.

Animation Options

Range Control options

Time Slider

Uses the start/end range from the time slider instead of the settings in this window.

Enabled

Click to quickly disable any animation without resetting the ranges.

Start/End

The Start value specifies the frame to start the output from (integer values). The End value specifies the frame to end the output.

Step

This value defines the number of animated frames by which the animation is sampled between exported frames.

Export Options

These options determine what elements you want to export.

Hierarchy

World

A World hierarchy tells the RTG translator not to export hierarchy. This means that all vertices use world space.

Flat

A Flat hierarchy means one level of hierarchy. Selecting Flat means that transformations use world space and vertices use local space. There is no hierarchy/parenting information. This is the default Hierarchy selection.

Full

A Full hierarchy exports the full DAG tree hierarchy. This means that transformations and vertices use local space. Full hierarchy/parenting information is also available.

Joints

Allows NULL chains to be output for hierarchy information, mostly for skeletons/joints.

Export

All

Exports all scene information (everything visible in the scene). This is the default Export selection.

Picked

Exports everything picked in the scene (items lower in the DAG tree from the DAG nodes of picked objects are not included).

Active

Exports everything picked in the scene as well as any objects that are below them in the DAG tree.

Tessellation

Tri

Tessellates NURBS surfaces into triangles. This is the default Tessellation selection.

Quad

Tessellates NURBS surfaces into quads.

Include

Cameras

Allows Camera information to be collected for the database. This option is on by default.

Lights

Allows Light information to be collected for the database. This option is on by default.

Debug Info

Geo/Mat

Outputs a lot of information during the export process. Shape/material information is output here.

Cameras

Controls camera process information.

Lights

Controls light process information.

Texture Options

Texture control

Evaluate

Uses convertSolidTx to create image files for both file and procedural textures. If turned off, Maya reads in the file textures as they are, and only converts the procedural textures.

Sample

Uses the 2D texture placement transformation information to generate the file image for output. For instance, the checker texture image consists of a checker board of 8x8 checkers. If Sample is off, the UV repeats are set to 1 internally, UV Rotate is set to 0.0 internally, and then the texture is processed. The result is that the checker image will be 2x2 (assuming the default 4 repeat).

Original

For file texture images, turn on to use a reference to the original file texture as defined in the texture node.

Resolution settings

Set the following X and Y texture resolution swatch sizes by entering a value and pressing Enter (IRIX, Linux and Windows)/Return (Mac OS X) or dragging the slider.

X Tex Res/Y Tex Res

Specifies the X or Y swatch size used for procedural textures.

Max X Tex Res/Max Y Tex Res

Specifies the Max X or Y swatch size used for all textures. If the size of file texture images is larger than the maximum specified here, then the file textures will be scaled down to this maximum setting when the convertSolidTx command is processed.

Texture Search path

This is a list of directories to search for file textures if not found in the default list of directories obtained with workspace -q -rd .

4 Game Exchange 2 Translator

Developer Games data translators

Games exchange 2 translator

Overview of GE2 translator

The GE2 translator lets you export Maya scene files into GE2 format.

GE2 Features

The following lists GE2 “Outputs” and “Files required to use this plug-in”.

Outputs

- polygon geometry
- NURBS surfaces - tessellated into either triangles or quads
- hierarchy structure if wanted
- shader parameters
- textures - possible formats are: SGI RGBA, Alias wirefile, bmp, png, ppm, and tif

Note GE2 export does not properly produce .bmp format image files for converted textures. We suggest you specify .sgi or .tif format instead, and convert the textures to .bmp.

- TRS animation
- vertex animation

Commands

Use the ge2tags script to assign ge2 properties to Maya shaders. This command adds a set of extra attributes to all Maya shaders, and directs the Attribute Editor to display the new attributes in a tabbed, easy-to-manage format.

Attributes

The ge2tags script assigns extra attributes to shaders to correspond with ge2 Material attributes. These can be edited and queried just as any other attributes.

Files required to use this plug-in

The files required for use of this plug-in are:

- ge2Export.lib (Mac OSX), ge2Export.so (IRIX and Linux), or ge2Export.mll (Windows)
- ge2TranslatorOpts.mel
- ge2tags.mel
- ge2MatAttr.mel
- AElambertGe2Revision.mel
- Source code can be found in: devkit/obsolete/games/ge2Export

Install the GE2 translator

You install the vrml translator plug-in using the Plug-in Manager.

To load the plug-ins

1. Select **Windows > Settings/Preferences > Plug-in Manager** to display the list of all known plug-ins.
2. Click the loaded or auto load check box to load one of the ge2Export.mll, or ge2Export.so, or ge2Export.lib plug-ins.

Menus

File

File > Export All > GE2

Domain Options

Click to turn on the options. A check mark displays if the option is on and the option you select will be enabled during output. The checked domains will be filled with the material attributes.

Format data for domain:

Options include: GL/DirectX, SonyPSX, N64, Custom

Animation Options

Enable Animation

Click to quickly disable any animation without resetting the ranges.

Start/End

The Start value specifies the frame to start the output from (integer values). The End value specifies the frame to end the output.

Step

The Step option is only available when the Keyframe using Anim Curves option is turned off. This value defines the number of animated frames by which the animation is sampled between exported frames.

Animate options

Click to turn the following options on or off.

Vertices

If on, Vertices exports vertex animation.

Transforms

If on, Transforms exports TRS animation.

Lights

If on, Lights animates the lights in the scene.

Camera

If on, Camera animates the camera in the scene.

Keyframe using options

Click to turn the following options on or off.

Anim Curves

If on, Anim Curves extracts keyframes from the AnimCurves on the shapes. If this option is selected, Step is set to 1 and disabled to ensure keyframes will fall on exported frames. If off, Step is enabled and you can change the default value.

Sampling

When on, Maya adaptively samples the animation. If this option is selected, Sample By and Tolerance are enabled. Frames are sampled at the given rate and exported as keyframes if geometry does not meet tolerance requirements.

Sample By

You must select Sampling in the Keyframe Using section to enable this option. This value represents the sample rate for adaptive sampling.

Tolerance

You must select Sampling in the Keyframe Using section to enable this option. This value determines whether sampled frames are exported as keys.

Animation Displacement options

These options are only enabled if you select Vertices in the Animate section.

- Relative to Current Frame specifies relative vertex displacements.
- Absolute generates absolute vertex displacement.

Export Options

These options determine what elements you want to export and how to export them.

Hierarchy

World

A World hierarchy tells the GE2 translator not to export hierarchy. This means that all vertices use world space.

Flat

A Flat hierarchy means one level of hierarchy. Selecting Flat means that transformations use world space and vertices use local space. There is no hierarchy/parenting information. This is the default Hierarchy selection.

Full

A Full hierarchy exports the full DAG tree hierarchy. This means that transformations and vertices use local space. Full hierarchy/parenting information is exported.

Export

All

Exports all scene information (everything visible in the scene). This is the default Export selection.

Selected

Exports everything picked in the scene (items lower in the DAG tree from the DAG nodes of picked objects are not included).

Active

Exports everything picked in the scene as well as any objects that are below them in the DAG tree.

Tessellation

Tri

Tessellates NURBS surfaces into triangles. This is the default Tessellation selection.

Quad

Tessellates NURBS surfaces into quads.

Export

If these options are on, (by default, all the Export options are on), Maya exports information for lights, cameras, textures, geometry, and normals.

Export options

The following options are off by default.

Reverse winding

If on, Maya enables reverse winding on polygons. Default winding is counter-clockwise.

Flip Normals

If on, Maya reverses the direction of normals. This option is off by default.

Texture Options

Texture Control

Uses convertSolidTx to create image files for both file and procedural textures. If turned off, Maya reads in the file textures as they are, and only converts the procedural textures.

Use 2d and 3d texture placement

Uses the 2D texture placement transformation information to generate the file image for output. For instance, the checker texture image consists of a checker board of 8x8 checkers. If off, the UV repeats are set to 1 internally, UV Rotate is set to 0.0 internally, and then the texture is processed. The result is that the checker image will be 2x2 (assuming the default 4 repeat).

Use convertSolidTx on file textures

This is a future option and is not currently implemented.

Use original file textures

If on, Maya reads in the file textures as they are, and only converts the procedural textures. If off, both procedural and file textures are converted.

Resolution settings

Set the following X and Y texture resolution swatch sizes by entering a value and pressing Enter (IRIX and Linux and Windows)/Return (Mac OS X) or dragging the slider.

X Tex Res/Y Tex Res

Specifies the X or Y swatch size used for procedural textures.

Max X Tex Res/Max Y Tex Res

Specifies the Max X or Y swatch size used for all textures. If the size of file texture images is larger than the maximum specified here, then the file textures will be scaled down to this maximum setting when the convertSolidTx command is processed.

Texture Search path

This is a list of directories to search for file textures if not found in the default list of directories obtained with workspace -q -rd.

Other Options

Float precision

Select a menu item to print out floats with the number of decimal places you choose.

Format Output

Tabs

If on, output is tabbed for readability. This option is on by default.

Comments

If on, output is commented (numbered indices, etc.). This option is off by default.

Debug Output

The following options are off by default.

Geometry

If on, Maya outputs information pertaining to geometry and anything attached to geometry (including materials) during the export process. A lot of information is generated during this process.

Cameras

If on, Maya outputs information about cameras during the export process.

Lights

If on, Maya outputs information about lights is during the export process.

Run script when done

Specify a script (and command line options) to be run after export to convert ge2 files to another file format or otherwise post-process the files.

Append file name to script

If on, the appropriate file (.grp or .gaf file) will be appended to the script you specify in Run script when done before invoking.

Game Exchange 2 Translator | 4
Developer > File > Export All > GE2

5 MDt API

Developer Games data translators

Games export toolkit (MDt API)

Overview of Games export toolkit

Important note: We encourage you to use Maya's API directly. Several new functions have been added to API since the MDT layer was created for Maya 1.0 which means the need to use the MDT layer has reduced. The source code has also been moved to: devkit/obsolete/games.

The MDt API is an implementation of the GAME EXPORT toolkit for Maya. It is a wrapper layer around the Maya API. Its main purposes are:

- To enable reuse of common code in multiple translators.
- Ease conversion of PA game translators over to Maya.
- Provide a level of grouping information obtained from the Maya API.
- Provide an additional source of Maya API examples.

Note: The MDt Api *DOES NOT* replace the Maya API. MDt Api functions work by using the Maya API.

Incorporate functions/ideas

The MDt Api compiles into a static library which the translators can be linked with. The files that make up the MDt Api library are:

MDtShape.cpp	geometry grouping (vertices, normals, colors, tessellation)
MDtMaterial.cpp	shaders, generating texture images, material properties
MDtLayer.cpp	miscellaneous control functions/startup/cleanup
MDtLight.cpp	light parameters

MDtCamera.cpp	camera parameters
MDtCnetwork.cpp	not used currently

iffreader.cpp	class to read iff files
iffwriter.cpp	class to write iff files

MDt.h	main header file for MDtApi
MDtExt.h	extension functions for MDtApi, access to original Maya objects so that the Maya API can be used with them.

Use the MDt library

The MDt library works by walking through the DAG structure of the scene and creating internal data tables that are then referenced by the MDt functions. This process can take a bit of time for large files or NURBS surfaces. If it takes too much time to generate the internal data tables, using the Maya API directly may better suit your needs.

Once the data tables are created, the translator is then able to access the tables and output the data in whatever format it needs to. References to the original Maya objects are stored (temporarily) so they can be referenced to get additional data without having to walk the DAG tree again.

Start with MDt functions and then use Maya API to obtain information that is not cached in the MDt data tables.

Tip	It is not recommended that you start with the Maya API and add in the MDt functions. The MDt functions can be used to quickstart or prototype a translator, and then use the knowledge gained to refine/customize the translator.

Find API function documentation

The documentation for the MDt API is integrated into the source files themselves where possible.

Use the MDt API

The MDt API is an example of how to use the Maya API. It is not the only method of obtaining Maya scene information from Maya. It is a combination of Maya API functions and executing MEL commands to get access to the data.

MDt API is not meant to replace Maya API in any way. It is grown and functions are added when deemed that something is of common interest to multiple uses. For example, not all of the Shader attributes are cached in the database. Those that are static and found to be used repeatedly are cached, but the API allows for the original Maya Object to be referenced to obtain additional data that is needed. It can be thought of as a higher level grouping function of common routines.

The two-stage process of generating the internal database and then running a translator with that data is a very general implementation. The scanning of the DAG tree and populating the internal database takes time. It is possible to write faster translators using the Maya API functions directly. The approach used for the VRML2 and other MDt based translators was to reduce the amount of work that had to be redone for each translator, and to reuse what was possible from pre-existing translators.

The VRML2, RTG, and GE2 game translators have been implemented as "file translators". They could also be implemented as normal Maya MPxCommand plug-ins.

Structure of the internal database

The database that is generated by the walking of the DAG tree is controlled by user options that are set/defined in the option box of the file translators.

The information gathered for the database consists of:

Shapes, Groups, Materials, Textures, Lights, and Cameras

Controls

These options are described in the sections for each of the games translators using the MDt API.

There is a lot of flexibility in the settings that can be set. The source code is also supplied so that additional options can be added for local customizations.

The options are implemented in the file *MDtLayer.cpp* and the header file *MDtExt.h*. It is possible to add additional control flags to the source code and also modify the MEL option scripts to set/reset the options.

This would also then modify the MDt files that implement the particular area of interest for the option. The translator Option MEL script file would then be modified to pass the values of the options to the translator itself.

Shapes

Shapes are the basic transformation/joint/polygonal/NURBS geometry objects. Each "shape" has an associated number of parameters.

- Transformations
- Materials/Groups
- Parents

Each shape also has an associated list of Groups. If the shape is a pure transformation/joint node then the number of groups will be Zero (for instance, no shader assignments). This usually only occurs when the hierarchy is set to FULL, or all of the transformations are flattened out, and geometry is associated with all of them.

Some API functions that operate using the Shape index are:

- DtShapeGetCount() - returns the number of shape nodes found.
- DtShapeGetMatrix(idx, *matrix) - returns the transformation matrix for shape idx, in the variable matrix

In general it is faster to use the geometry from the ByShape based functions rather than those of the ByGroup family. There isn't a second copy of the data generated and passed by to the caller.

The Shape functions are found in the source file MDtShape.cpp.

Groups

Groups are subsets of its Shape, that are defined by multiple shader assignments to it. For a NURB object there would be at most 1 group. For polygonal objects there would be 1 group for each shader that is assigned to that object. If there are no shaders assigned to the polygonal object then the number of groups will be zero. In this case it is most likely to be a transformation node of some kind.

The ByGroup functions need to allocate memory to generate the lists that are returned. Since the API functions don't know when that memory is no longer used, it is up to you to free it when done with the returned lists.

The *MDtShape.cpp* file implements these functions.

Materials

Materials are the shaders found in the DAG tree walk.

For each shader that is found, a reference is stored for it, and can be accessed by either "name" or ID number. From the reference it is possible to use the Maya API directly to obtain the shader parameters of interest.

The *MDtMaterial.cpp* file implements these functions.

Textures

Textures are the textures mapped for the shaders. By default, only the color and transparency textures are evaluated and a combined rgba file image is generated in memory. It is possible to enable extra processing to output all or most of the textures mapped on a shader, this is part of the "MultiTexture" option.

The *MDtMaterial.cpp* file implements these functions

Lights

Lights information is gathered and made available. Similarly to Materials, a reference is temporarily saved to access the light parameters of interest.

The *MDtLights.cpp* file implements these functions

Camera

Camera information is gathered and made available. Similarly to the Materials, a reference is temporarily saved to access the camera parameter of interest.

The *MDtCamera.cpp* file implements these functions

Utility

There are some utility functions that allow for decomposing matrices, and other general functions. This are found in the *MDtLayer.cpp* file along with the control options for the DAG walk processing

Animation

Obtaining animation data out of the MDt functions is the same as getting the non-animation data out.

When the DAG tree is walked for generating the internal database, the references that are saved are used to obtain the geometry/material information that is needed.

Iterating over a range of animation, it is then accomplished with the DtFrameSet(frame) call which sets the current frame time. Maya automatically updates its dependency graph.

For each frame, DtFrameSet then updates the parameters that are wanted. Currently, this is mostly the geometry (vertices, normals, uvs) so the same function calls are reused to get the new frames geometry data.

The transformation data is obtained by referencing the transformation object. This data is not cached.

We recommend that you iterate over the animation range as few times as possible. See the following example:

```
for ( animation = start, to end )
      for ( shape = 0, to last Shape )
            get and save TRS data for shape
      next shape
next frame
```

Minimal Program example

The bare minimum plug-in to use the MDt functions consist of:

- initializing the internal database
- walking the Maya scene graph and populating the database
- freeing the internal database

The following code snippet shows the functions that would need to be called. This snippet doesn't actually output anything. There would normally be additional calls to customize the method of populating the internal database and actual calls to retrieve and output the data itself. This is just a sample.

```
// Initialize the internal database with a scene "name"
DtExt_SceneInit( "basic" );
//Now we can setup the database from the wire file geometry
DtExt_dbInit();
// Clean house.
DtExt_CleanUp();
```

Basic Program example

The following is a basic Dt based plug-in that queries the selected objects and outputs the name of the shape (mesh) and any "color" texture file names that are mapped to the shader.

```
#include <maya/MSimple.h>
#include <MDt.h>
#include <MDtExt.h>
DeclareSimpleCommand( basic, "Alias - Example", "2.0");

void outputFileNames()
{
char *shapeName;
char *mtlName;
char *texName;
```

```
// 1st thing find out how many shapes (meshes) are in this
scene
// currently being looked at.
int numShapes = DtShapeGetCount();
// For each shape, check out what is assigned as the color
texture
// There may not be a texture associated with material, or
the texture
// may be a procedural texture and so have no file name.
for ( int shape=0; shape < numShapes; shape++ )
{
// Find the name of the current shape that we are looking
at.
DtShapeGetName( shape, &shapeName );

// Find out the number of groups (materials) assigned to
this shape
numGroups = DtGroupGetCount( shape );
// For each group (material) check out to see if there is a
file texture
// associated with the material and output its name.
// It is possible that the number of groups will be zero.
In this case
// there would be no materials assigned:
// 1) Joint or other Transform node
// 2) user deleted all of the materials including the
default shading group
// 3) removed the connections between the mesh and the
shading groups.
// Usual reason is #1, a Joint or straight Transform node.
(when using
// full hierarchy mode
    for ( int group=0; groups < numGroups; group++ )
    {
       // For the current shape+group combination find out
its material

       DtMtlGetName( shape, group, &mtlName );

       // For the current material, find out its texture
file name if any

       DtTextureGetFileName( mtlName, &texName );

       // output any information that is wanted about what
we found above.

       printf( "for shape %s(%d) group %s(%d), texture
filename is %s\n",
```

```
                shapeName, shape, mtlName, group, texName ?
texName : "(NULL)" );
    }
  }
}
//
// main doIt function for the plugin command.
MStatus basic::doIt( const MArgList& args )
{
// Initialize the Dt database
DtExt_SceneInit( “basic” );
// using the default settings, as no initializer
// functions are called here
// Walk the dag and fill in the internal database
DtExt_initdb();

// walk thru shapes found and output the texture file names
outputFileNames();


// Clean up the allocated memory and internal storage
DtExt_CleanUp();
// return from the plugin command
return MS::kSuccess;
}
```

Index

Numerics

2D/3D texture placement
GE2 Texture Option 37

A

Active
GE2 Export Option 36
RTG Export Option 31
VRML2 Export Option 22
Add and Update checkBox
VRML2 18
All
GE2 Export Option 36
RTG Export Option 31
VRML2 Export Option 21
All Nodes 29
RTG Output Option 29
Animation 29
RTG Output Option 29
animation
displace for GE2 36
MDt API description 45
sample for GE2 35
tolerance, set for GE2 36
animation playback
loop, for VRML2 20
Any
VRML2 Output Option 24
append file name
to scripts, for GE2 39
to scripts, for VRML2 25

B

browse
scripts, for GE2 39
scripts, for VRML2 25
ByGroups
MDt API description 44

C

Camera
GE2 Animate Option 35
RTG Export Option, debug info 31
RTG Export Option, Include 31
camera
animate, for GE2 35
Cameras
GE2 debug info 38
VRML2 debug info 21, 22
VRML2 Export Option, Include 22
cameras
MDt API description 45
color
per vertex, export
VRML225
ColorPerVertex
VRML2 Export Option 25
Comments
GE2 Output option 38
Compressed
VRML2 Export Option 25
Custom
GE2 Output Domain option 34

D

debug info
Camera for RTG 31
Cameras for GE2 38
Cameras for VRML2 . . . . . 21, 22
Geo/Mat for RTG 31
Geo/Mat for VRML2 22
geometry for GE2 38
Lights for GE2 39
Lights for RTG 31
Lights for VRML2 22
Degrees
RTG Output Option, Format 29
digits
number of, for VRML2 output 24
Displacement
GE2 Animation Option 36

Domain Options
GE2 Output options 34

E

Enabled
RTG Animation Option 30
VRML2 Animation Option. 20
Evaluate
RTG Export Option, Texture 32
VRML2 Export Option, Texture 22
Examine
VRML2 Output Option. 24

F

file textures
use original, for GE2 37
Flat
GE2 Export Option, Hierarchy 36
RTG Export Option, Hierarchy 30
VRML2 Export Option, Hierarchy 21
flip
normals, for VRML2 24
normals, using GE2 37
Flip Normals
GE2 Export Option 37
Float precision
for GE2 38
float precision
for VRML2 output 24
Fly
VRML2 Output Option. 24
Frames per sec
VRML2 Animation Option. 20
Full
GE2 Export Option, Hierarchy 36
RTG Export Option, Hierarchy 30
VRML2 Export Option, Hierarchy 21

G

games translators
build 9
GE2, install 34
installing 10
recompile 8
RTG, install. 27
running 8
VRML2, install 15
GE2
browse scripts for 39
Cameras debug info 38
Domain Options 34
features 33
file name, append to scripts. 39
Geometry debug info 38
install translator. 34
Lights debug info. 39
Output Options 34
Texture Search Path. 38
translator options 34
GE2 Animate Option
Camera 35
Vertices 35
GE2 Animation Option. 35
Start/End 35
GE2 Displacement Option
Animation option 36
GE2 Export Option
Active 36
All 36
Flat hierarchy 36
Flip Normals 37
Full hierarchy. 36
Reverse winding 37
Selected 36
Tri Tessellation. 37
World hierarchy. 36
GE2 Keyframe Option
Sample animation 35
Tolerance, set for animation. 36
GE2 Texture Option
2D/3D texture placement 37
textures, set resolution for 38
use original file textures 37

Geo/Mat
RTG Export Option, debug info 31
VRML2 debug info 22
Geometry
GE2 debug info 38
GL/DirectX
GE2 Output Domain option. 34
gzip
compress output file
VRML225

H

Headlight
control, for VRML2 output. 24
hierarchy
Flat, GE2 Export Option 36
Flat, RTG Export Option. 30
Flat, VRML2 Export Option 21
Full, GE2 Export Option 36
Full, RTG Export Option 30
Full, VRML2 Export Option. 21
World, GE2 Export Option. 36
World, RTG Export Option 30
World, VRML2 Export Option 21

I

iffreader.cpp 42
iffwriter.cpp 42
importing
VRML2 18
IndexCnt 29
RTG Output Option 29
IRIX and Linux/DOS
RTG Output Option, Format 28

J

Joints
RTG Export Option 21, 30

L

Launch viewer
VRML2 Export Option 25
lighting
control, for VRML2 output 24
Lights
GE2 debug info 39
RTG Export Option, debug info 31
RTG Export Option, Include 31
VRML2 Animate Option 21, 35
VRML2 debug info 22
VRML2 Export Option, Include 22
lights
animate, for VRML2 . . . . . 21, 35
MDt API description. 45
Local Xform 29
RTG Output Option 29
Long Lines
VRML2 Export Option 25
Loop
VRML2 Animation Option 20

M

Materials 29
RTG Output Option 29
VRML2 Animate Option 21
materials
MDt API description. 44
shader, animate, for VRML2 21
MDecomp 29
RTG Output Option 29

MDt API
animation, description 45
ByGroups, description 44
cameras, description 45
controls, description 43
description 41
groups, description 44
lights, description 45
materials, description 44
program example, basic 46
program example, minimal 46
shapes, description 44
textures, description 45
using 43
MDt library
using 42
MDt.h 42
MDtCamera.cpp 42, 45
MDtCnetwork.cpp 42
MDtExt.h 42, 43
MDtLayer.cpp 41, 43
MDtLight.cpp 41
MDtLights.cpp 45
MDtMaterial.cpp 41, 45
MDtShape.cpp 41, 44
MultiTexture 29
RTG Output Option 29

N

N64
GE2 Output Domain option 34
navigation
remove UI for VRML2 24
Navigation Speed
for VRML2 output 24
Normals
VRML2 Export Option 24
normals
export, for VRML2 24
flip, for VRML2 24
flip, using GE2 37

O

Opposite
VRML2 Export Option 24
output
editing, for VRML2 25

P

P Normals
RTG Output Option, Format 28
Picked
RTG Export Option 31
VRML2 Export Option 22
Pivots 29
RTG Output Option 29
playback
animation, for VRML2 20
polygons
flip normals, using GE2 37
reverse winding, with GE2 37

Q

Quad
RTG Export Option, Tessellation 31, 37
VRML2 Export Option, Tessellation 22

R

Resolution
GE2 Texture Option, set for textures 38
RTG Export Option, set for textures 32
VRML2 Export Options, set for textures 23
Reverse winding
GE2 Export Option 37
Reversed
RTG Output Option, basic 28
VRML2 Export option 25
RTG
features 27
install translator 27
translator options 27

RTG Animation Option 30
Enabled 30
Time Slider 30
RTG Export Option
Active 31
All 31
Camera debug info 31
Camera, include 31
Evaluate texture 32
Flat hierarchy 30
Full hierarchy 30
Geo/Mat debug info 31
Joints 21, 30
Lights debug info 31
Lights, include 31
Picked 31
Quad Tessellation 31, 37
Sample texture 32
Texture Search Path 32
textures, set resolution for 32
Tri Tessellation 31
World hierarchy 30
RTG Output Option 28, 29
Degrees format 29
IRIX and Linux/DOS formats 28
P Normals format 28
Reversed, basic 28
V Colors format 28
V Normals format 28
Verbose, basic 28

S

Sample
GE2 Keyframe Option 35
RTG Export Option, Texture 32
VRML2 Export Option, Texture 23, 32
Sample By
GE2 Keyframe Option 35
scripts
append to, for GE2 39
append to, for VRML2 25
browse for GE2 39
browse for VRML2 25
search path
for textures, GE2 38
for textures, RTG Export 32
for textures, VRML2 Export 23, 25
Selected
GE2 Export Option 36
shader materials
animate, for VRML2 21
SonyPSX
GE2 Output Domain option 34
Start/End 30
GE2 Animation Option 35
RTG Animation Option 30
VRML2 Animation Option 20
Step 30, 35
GE2 Animation Option 35
RTG Animation Option 30
VRML2 Animation Option 20

T

Tabs
GE2 Output option 38
Texture Search path
GE2 38
RTG Export Options 32
VRML2 Export Options 23, 25
Textures
VRML2 Export Option 25
textures
evaluate for RTG 32
evaluate for VRML2 22
export, for VRML2 25
file, use original, for GE2 37
MDt API description 45
place 2D/3D for GE2 37
sample for RTG 32
sample for VRML2 . . . . . 23, 32
search path for GE2 38
search path for RTG Export 32
search path for VRML2 Export 23, 25
Time Slider
RTG Animation Option 30
VRML 2 Animation Option 20

Tolerance
GE2 Keyframe Option. 36
Transf
VRML2 Animate Option 20, 35
transformations
animate, for VRML2 . . . . . 20, 35
Transforms 29
RTG Output Option 29
translator
install GE2. 34
install RTG 27
install VRML2 15
translators
build, for games 9
installing, for games 10
recompile, for games. 8
running, for games 8
VRML2, introduction 13
Tri
GE2 Export Option, Tessellation 37
RTG Export Option, Tessellation 31
VRML2 Export Option, Tessellation. 22

U

UI
remove navigation, for VRML2. 24
UV Coords. 29
RTG Output Option 29

V

V Colors
RTG Output Option, Format 28
V Normals
RTG Output Option, Format 28
V1.8 Compatible
RTG Output Option, Format 28
V1.8 Compatible format 28
Verbose
RTG Output Option, basic 28
VRML2 Export Option 25
Vertices
GE2 Animate Option. 35
VRML2 Animate Option 20
vertices
animate, for GE2 35
animate, for VRML2 20
viewer
launch, for VRML2 25
viewpoints
creating with VRML2 17
VRML 2 Animation Option
Time Slider 20
VRML Output Option
Any 24
Examine 24
Fly 24
Walk. 23
VRML2. 18
attributes. 13
browse scripts for 25
Cameras debug info 21, 22
commands 13
features 13
file name, append to scripts. 25
files. 14
Float precision option 24
float precision setting 24
for UNIX 18
for Windows. 18
Geo/Mat debug info. 22
Headlight options 24
install translator. 15
introduction 13
lighting, for output 24
Lights debug info. 22
Navigation speed option 24
navigation speed, output for 24
options. 19
Output navigation check box 23
remove navigation UI. 24
translator options 15
viewpoints, creating 17
VRML2Link, linking objects with 16
vrml2Tags command, setting 15
VRML2 Animate Option
Lights. 21, 35
Materials 21
Transf. 20, 35
Vertices 20

VRML2 Animation Option
Enabled . . . 20
frames per sec. . . . 20
Loop. . . . 20
Start/End . . . 20
Step . . . 20
VRML2 Export Option
Active. . . . 22
All. . . . 21
Cameras, include . . . 22
ColorPerVertex. . . . 25
Compressed . . . 25
Evaluate texture . . . 22
Flat hierarchy . . . 21
Full hierarchy . . . 21
Launch viewer . . . 25
Lights, include . . . 22
Long Lines . . . 25
Normals. . . . 24
Opposite . . . 24
Picked . . . 22
Quad Tessellation . . . 22
Sample texture . . . 23, 32
Texture Search Path. . . . 23, 25
Textures. . . . 25
textures, set resolution for . . . 23
Tri Tessellation . . . 22
Verbose . . . 25
World hierarchy. . . . 21
VRML2 Output Option
Reversed . . . 25
VRML2Link . . . 16
vrml2Tags
command . . . 15
setting . . . 15
window . . . 15
vrml2TagsWin
Add and Update checkbox . . . 18
Add button . . . 18
attributes, descriptions . . . 17
Close button . . . 18
Delete button . . . 18
Do All selected checkbox . . . 17
stepping control buttons . . . 18
vrml2 Billboard menu. . . . 17
vrml2 Sensor menu . . . 17
vrml2tagsWin
vrml2 Collision menu . . . 17
vrmls2TagsWin
vrml2 primitive menu. . . . 17

W

Walk
VRML2 Output Option. . . . 23
World
GE2 Export Option, Hierarchy . . . 36
RTG Export Option, Hierarchy . . . 30
VRML2 Export Option, Hierarchy . . . 21
wrl2ma
UNIX VRML2 import . . . 18
wrl2ma.exe
Windows VRML2 import. . . . 18

Index